

How to Setup PureVPN Manually on Windows Vista (OpenVPN) ?

Things to Consider:

Before you begin, please make sure that:

- You have a working internet connection
- Windows Supported Device.
- A Premium PureVPN account (If you haven't bought yet click [here](#) to buy)

Find your VPN credentials for manual configuration.

- Login to the PureVPN [member area](#)

PureVPN Support

Solution of Your Problems

• Note down your PureVPN username and click on Eye icon to make your password visible
<https://support.purevpn.com>
and use it in the manual configuration.


How to connect PureVPN manually on Windows Vista.

1 Download PureVPN [OpenVPN](#) installer.

2 Right click on [OpenVPN installer](#) and select properties.




3 From General Tab, click on “Unblock”, “Apply” and “OK”




4 Right click on OpenVPN installer and select “Open” or Double click to execute




5 Click “Continue” to allow installation




6 Click “Next”




7 Click “I agree”




8 Click “Next”




9 Click "Install" to begin installation



10 Click “Next” once installation completes



11 Uncheck “Show Readme” and click on Finish




Connecting OPENVPN:


12 Right click on OpenVPN GUI icon and “Run as administrator”




13 Click “Continue” to allow application to run




14 Right click on OpenVPN icon from System tray, go to desired server and select “Connect”



15 Insert Username and Password provided by PureVPN




16 VPN will establish connection in few seconds



17 You are connected now. Enjoy the Freedom!




18 To disconnect OpenVPN. Right click on OpenVPN Icon from System tray, go to connected server and select "Disconnect"




Saving account details:


19 Right click on OpenVPN Icon from system tray, go to desired server and select Edit Config




20 Add pass.conf after auth-user-pass parameter and save




21 Open notepad and insert Username in first line and password in second line then save it as pass.conf




22 Open folder where you save the file, click on Tools menu and select Folder options




23 Click on View tab and uncheck “Hide extensions for known file types”, click “Apply” and “OK”




24 Right click on pass.conf.txt file and rename it




25 From pass.conf.txt, remove .txt, hit enter and click on “Yes” to continue




26 Open OpenVPN installation folder (C:\Program Files\OpenVPN\config) and drag / copy pass.conf file in config folder



27 Click “Continue” to copy file



28 Click “Continue” to allow



***Repeat Step 19 and 20 to edit all servers**

Step19: Right-click on OpenVPN Icon from the system tray, go to the desired server and select Edit Config

Step20: Add pass. conf after auth-user-pass parameter and save

Having Trouble Connecting?

If you're still unable to connect, then please check the most common errors and their solutions

Error 868

[Solution](#)

Error 800, 806, 807, 809

[Solution](#)

Error 720

[Solution](#)

Error 691
[Solution](#)

Error 647
[Solution](#)