

## How to Setup PureVPN on Arris Router

If you want to set up a VPN with PPTP on your Arris router, follow this step-by-step guide.

### Things to Consider:


Before you begin, please make sure that:

- You have a working internet connection
- VPN Supported Router.
- Own a premium PureVPN account (If you do not already own one, you can buy a subscription from [here](#))

1 This image shows how your VPN setup will look like this:

1a. Shows an Ethernet connection from the router to a computer.

1b. Shows a wireless connection from the router to the computer.



In order to set up a PPTP connection on your Arris router, please access your router first.

Under WAN Setup, please change your Connection Type to PPTP.

Then select the following options:

2 Check Enable PPTP

3 Enter your PureVPN username and password

4 Enter your Server Address: Use one of our server names from this list, [click here](#).

5 Enter My Internet IP: Get automatically from ISP. If there is no such setting, please skip it

6 ForMy IP Address: leave blank


7 My Subnet Mask: leave blank

8 Enable Idle Timeout

9 Idle timeout: 300

10 Enable Keep-alive

11 Keep-Alive: 30



The image shows a screenshot of an ARRIS router's web interface. At the top, there is a navigation bar with the ARRIS logo and buttons for 'Wireless', 'HSD', and 'Logout'. Below this is a secondary navigation bar with buttons for 'Basic Setup', 'WAN Setup', 'LAN Setup', 'Wireless Setup', 'Firewall', and 'Utilities'. The main content area is titled 'PPTP Connection Type'. On the left, there is a sidebar menu with options: DYNAMIC, STATIC, DYNAMIC (IPv6), STATIC (IPv6), DS-LITE, and PPTP (which is highlighted in yellow). The main content area contains a paragraph explaining PPTP and a 'PPTP Settings' section with various input fields and checkboxes. At the bottom left of the settings area, there is a red-bordered 'Apply' button.

## PPTP Connection Type

If your Internet Service Provider has specially told you to use PPTP and has supplied you with the proper PPTP configuration information, then use this option. For changes to take effect you must click the Apply button.

### PPTP Settings

Enable PPTP	<input type="checkbox"/>	?
Account	PureVPN Username	?
Password	PureVPN Password	?
Retype Password	PureVPN Password	?
Server Host Name	PureVPN Server Address	?
Server Address	ISP IP	?
My IP Address		?
My Subnet Mask	0.0.0.0	?
Enable Idle Timeout	<input type="checkbox"/>	?
Idle Timeout	30	?
Enable Keep Alive	<input type="checkbox"/>	?
Keep Alive	30	?

**Apply**