

## How to Setup PureVPN on D-Link Router?

To be able to take advantage of PureVPN across any and all devices via your D-Link router, We used the D-Link DIR 842 (Firmware Version L 2.x) for this how-to. There are so many models of D-Link routers, and so not all of them can be entertained. However, this should give you a general idea of how the setup process will be, here is what you need to do:

### Things to Consider:

Before you begin, please make sure that:

- You have a working internet connection
- VPN Supported Router.
- Own a premium PureVPN account (If you do not already own one, you can buy a subscription from [here](#))


To Set Up PureVPN on a D-Link Router:

### 1 Review Network Model



## 2 Go to setup:

- Click on Internet tab on left hand navigation
- Click on Manual Internet Connection Setup



## 3 From my internet connection is select " PPTP(Username/Password) "

Under PPTP Internet Connection TYPE section.

- Select Address Mode: DYNAMIC
- Enter your Desired server address into the Server IP address field. Click [here](#) to get the Server List.

- Insert your username & password as provided by PureVPN. (For further instructions on how to check your active PureVPN username and password [click here.](#))
- Click on Save Settings

The screenshot displays the configuration page for a PureVPN router, specifically the WAN settings. The interface is divided into several sections:

- WAN:** This section provides instructions on configuring the Internet Connection type. It lists options like Static IP, DHCP, PPPoE, PPTP, and L2TP. A note states that if using PPPoE, any PPPoE client software on computers should be removed or disabled. There are two buttons: "Save Settings" and "Don't Save Settings".
- INTERNET CONNECTION TYPE:** This section asks the user to choose the mode for connecting to the Internet. The selected option is "PPTP (Username / Password)".
- PPTP INTERNET CONNECTION TYPE:** This section requires the user to enter information from their ISP. The "Address Mode" is set to "Dynamic IP". Other fields include:
  - PPTP IP Address: 0.0.0.0
  - PPTP Subnet Mask: 0.0.0.0
  - PPTP Gateway IP Address: 0.0.0.0
  - PPTP Server IP Address: your desired server name
  - Username: your\_purevpn\_username
  - Password: [masked]
  - Verify Password: [masked]
  - Reconnect Mode: On demand (selected)
  - Maximum Idle Time: 5 (minutes, 0=infinite)
  - Primary DNS Server: 0.0.0.0
  - Secondary DNS Server: 0.0.0.0
  - MTU: 1400 (bytes) (MTU default = 1400)
  - MAC Address: [masked]